

SNS Pink & White Refill



Items Needed

Natural Set, French White, Natural Pink, E.A. Bond, Gel Base, Sealer Dry, Gel Top, Vitamin Oil, French Mould



Preparation Steps

Always sanitize your customers hands with 100% alcohol, as well as your own hands, before performing any service.




Step 1

Using an electric nail machine with a medium or coarse carbide tip, remove 70% of the SNS nails and the lifting areas for all 10 finger nails.



Step 2

Using an electric nail machine with a FINE sandpaper drum, remove excess cuticles and the shine of the real nails.



Step 3

Apply **E.A. Bond** to all 10 nails (use a napkin to dry them well before applying the SNS Gel Base application).

Notice:

1. Always bend the finger 90 degrees before tapping the finger
2. When applying Gel Base, apply the brush laying flat and go from left to right (long strokes), then from right go evenly back to left (before any dipping)

Dipping Powder Steps

During Pink and White application, always work with **two fingers each time** until it is done.



Step 1

On the first finger, apply **Gel Base** to 3/4 of the nail.



Step 2

Slide your nail into the ***French White** powder using the French Mould. Tap the excess. Quickly dip into **Natural Set** powder, then tap the excess.



Step 3

Repeat steps 1 through 2 on the second finger.



Step 4

Go back to the first finger, apply **Gel Base** on the entire nail (3 hair lines away from the cuticles).



Step 5

Slide the first finger into the ***French White** using the French Mould, tap the excess. Quickly dip again in ****Natural Pink**, then tap the excess.



Step 6

Come back to second finger and repeat steps 4 through 5. Then apply **Sealer Dry** to both the 1st and 2nd finger.

*May use American White instead of French White

**May use Dark Pink, X Dark Pink, Pink F1, F2, or F4 instead of Natural Pink



Step 7

Repeat all steps for remaining nails.
Working with two nails at a time.

Notice:

1. If the nail has a low spot on the plate, you can apply very thin coat of Gel Base and quick dip into Natural Set Sheer then apply Sealer Dry.

Finishing Steps



Step 1

Shape all 10 nails* (may use the nail machine with fine paper sander around the cuticle and use with slow speed, in case the nail plate is waving).



Step 2

Buff all 10 nails and wash the hands.



Step 3

Apply **Sealer Dry** to all 10 nails, and then wipe them off with a paper towel.



Step 4

Apply the first coat of **Gel Top** quickly and as thin as possible for five nails, and then reapply the second coat in the same way. Repeat the same on the second hand.

Step 5

Wait for 1 to 2 minutes. Apply **SNS Vitamin Oil** and massage the hands to finish.



SNS Regular Set




Signature Nail Systems

Illinois, USA

1-888-445-2786

www.snsnails.com

Find us on 
snsnailproduct

Techniques were designed by SNS Company & Copy Right.